

**RANGE REGULATIONS FOR BISLEY SPORTING RIFLE
STATICS RANGE**

| THE RANGE | |
|--|---|
| Name | Statics (Sporting Rifle Complex) |
| Description | <p>Type: Gallery Range</p> <p>Danger area: Full Danger Area (FDA)</p> <p>Location (What3words): Then.Prone.Merit</p> <p>Distance: 20 - 100yds</p> <p>Targets:</p> <ul style="list-style-type: none"> • 7 Static electronic targets (6 firing points) <p>Additional notes: There is open access to other ranges within the BSR complex (see coordinating instructions below)</p> |
| FIREARMS AND AMMUNITION | |
| Permitted firearms and ammunition including ME & MV | <p>Type: Rifles; gallery rifles. Shotguns and pistols by special arrangement only</p> <ul style="list-style-type: none"> • Maximum Muzzle Velocity: 1000 m/s (3280 ft/s) • Maximum Muzzle Energy: 4500 J (3319 ft/lb) <p>HME Permitted: 4500J – 7000J HME procedures apply</p> <p>Special Requirements:</p> <ul style="list-style-type: none"> • Shooting forward of the 100x firing point is permitted for calibres up to a maximum muzzle velocity of 655 m/s (2150 ft/s) and muzzle energy of 2030 J (1496 ft/lb) • Muzzle brakes permitted with consent of adjacent shooters • Vermin calibre MR not exceeding 1350 m/s (4429 ft/s) may be used providing ME does not exceed 2600 J (1918 ft/lb) <p>Not Permitted:</p> <ul style="list-style-type: none"> • .22 Hornet • .22-250 • .220 Swift |
| RANGE SAFETY LIMITATIONS | |
| Coordinating Instructions | <ol style="list-style-type: none"> Shooting on this range affects the following ranges: <ol style="list-style-type: none"> BSR <ol style="list-style-type: none"> Running Boar Running Deer Melville Stickledown Pirbright Access: <ol style="list-style-type: none"> All movement forward of the Statics Range firing point requires the following ranges to have ceased fire: <ol style="list-style-type: none"> Statics Running Boar Running Deer When there are personnel forward of the firing points, the |

| | |
|-------------------------------------|--|
| | <p>red flag system is to be followed under the direction of the BSR Manager</p> <p>c. When shooting is conducted from the turning target firing points on Running Deer, the BSR Manager is to ensure demarcation lines are set up between Running Deer and Statics range to ensure safe access/egress</p> <p>d. When shooting is conducted forward of the statics firing point, the BSR manager is to ensure there is no shooting on the Running Boar or Running Deer ranges.</p> <p>3. Range infrastructure is not to be used as targetry or to zero/check zero firearms</p> <p>4. A Suitably Qualified Experience Person (SQEP) is to be appointed as the responsible RO when shooting</p> <p>5. Vehicles are not permitted on the range floor without prior permission from the BSR manager</p> |
| Firing positions | <p>6. Positions permitted:</p> <p>a. Prone</p> <p>b. Sitting</p> <p>c. Kneeling</p> <p>d. Standing</p> <p>e. Benched</p> <p>7. When shooters are firing from different positions there is to be a common firing line.</p> <p>8. Changes of position are permitted within any detail or practice outside competition providing all firers follow the same sequence, and in competition in accordance with the conditions</p> |
| Targetry | <p>9. MAX TCH: 1.5m</p> <p>10. Only targets from the BSR approved set may be used</p> <p>11. Targets are to be used in the frames or holders provided and are to be engaged only from the recognised firing points and/or appropriate shooting station or peg. Any deviation from this is to be notified and approved by the NSC Head of Operations.</p> <p>12. Falling Plates or other hard targets may not be engaged within Statics Range</p> |
| ACCIDENT/INCIDENT PROCEDURES | |
| Special Safety Instructions | As per the NRA Range Action Safety Plan which will be initiated by the Range Office on notification of a major incident/accident |